




# **USB-RELAY02 USB-RELAY04 USB-RELAY08**

**DRIVER INSTALLATION FOR WINDOWS 10 / 11**


**INSTALLATION DU DRIVER POUR WINDOWS 10 / 11**



## English:


1)

Right-click on the **Windows icon** at the bottom left of the screen.  
Then click on the **Device Manager** menu.




2)

Selects **Ports (COM & LPT)**.  
Then right-click on **PL2303HXA**.  
Select **Update driver**.




3)

In the window that opens, select **Browse my computer for drivers**.






4)

In the windows that opens, select **Let me pick from a list of available drivers on my computer**. Then click on **Next**.




5)  
Select **Prolific USB-to-Serial Comm Port Version 3.3.2.102 [24/09/2008]**.  
Then click on **Next**.






  Update Drivers – PL2303HXA PHASED OUT SINCE 2012. PLEASE CONTACT YOUR SUPPLIER.


Select the device driver you want to install for this hardware.

 Select the manufacturer and model of your hardware device and then click Next. If you have a disk that contains the driver that you want to install, click Have Disk.

☒ Show compatible hardware

Model

 Prolific USB-to-Serial Comm Port Version: 3.3.2.102 [24/09/2008]  
 Prolific USB-to-Serial Comm Port Version: 3.8.12.0 [03/03/2017]  
 Prolific USB-to-Serial Comm Port Version: 3.8.42.0 [22/02/2023]

 This driver is digitally signed.  
[Tell me why driver signing is important](#)

Have Disk...

Next

Cancel


6)  
The driver is being installed.




  Update Drivers – PL2303HXA PHASED OUT SINCE 2012. PLEASE CONTACT YOUR SUPPLIER.

Installing drivers...

7)  
Windows has completed the driver update.  
Click close to return to the **Device Manager**.




8)  
In the **Device Manager**, you can check that the device has been installed correctly



## Français:


1)

Faire un clic droit sur **l'icône Windows** en bas à gauche de l'écran.  
Cliquer ensuite sur le menu **Gestionnaire de périphériques**.



2)

Sélectionnez **Ports (COM et LPT)**.  
Puis faire un clic droit sur **PL2303HXA**.  
Sélectionnez ensuite **Mettre à jour le pilote**.






3)

Dans la fenêtre qui s'ouvre, sélectionnez **Parcourir mon poste de travail pour rechercher des pilotes**.




4)


Dans la fenêtre qui s'ouvre, sélectionnez **Choisir parmi une liste de pilotes disponibles sur mon ordinateur**. Puis Cliquer sur **Suivant**.



5)  
Sélectionnez **Prolific USB-to-Serial Comm Port Version 3.3.2.102 [24/09/2008]**.  
Puis cliquer sur **Suivant**.

←  Mettre à jour les pilotes - PL2303HXA PHASED OUT SINCE 2012. PLEASE CONTACT YOUR SUPPLIER.


Choisissez le pilote de périphérique à installer pour ce matériel.





Sélectionnez le fabricant et le modèle de votre périphérique matériel et cliquez sur Suivant. Si vous avez un disque qui contient le pilote que vous voulez installer, cliquez sur Disque fourni.


☒ Afficher les matériels compatibles

Modèle

 Prolific USB-to-Serial Comm Port Version : 3.3.2.102 [24/09/2008]

 Prolific USB-to-Serial Comm Port Version : 3.8.42.0 [22/02/2023]

 Prolific USB-to-Serial Comm Port Version : 3.8.43.0 [29/05/2024]

 Ce pilote a été signé numériquement.


Disque fourni...

[Pourquoi la signature du pilote est-elle importante ?](#)

Suivant

Annuler

6)  
L'installation du pilote est en cours.

←  Mettre à jour les pilotes - Prolific USB-to-Serial Comm Port (COM3)


Installation des pilotes...



7)

Windows a terminé la mise à jour du pilote.

Cliquer sur Fermer pour revenir au **Gestionnaire de périphérique**.



8)

Dans le **Gestionnaire de périphérique**, vous pouvez vérifier l'installation correcte du périphérique.

